

# SBB Widgets for Confluence

Get the app at the Atlassian Marketplace

- [Overview](#)
- [Stationboard Macro](#)
- [Parameter](#)
  - [Example](#)
- [Connections Macro](#)
- [Parameter](#)
- [Related articles](#)
- [Support](#)

## Overview

Look up SBB CFF FFS timetables and station boards from within Confluence.

## Stationboard Macro




**SBB Stationboard** {stationboard-macro}

See the next departures of your station

## Parameter

Name	Description	Type	This is a required field	Default	Values
<code>station</code>		string	✗		
Name of the station <code>id</code>	Enter the name of the station from which the next connections will be displayed.	string	✓		
Limit results <code>limit</code>	How many entries you like to see?	int	✗	15	
Change Station <code>showSearchBox</code>	Possibility to change the station.	boolean	✗	false	

## Example



17:14 +3 min	S8 18867	Pfäffikon SZ
17:15 +3 min	S1619667	Herrliberg-Feldmeilen
17:16	T 3	Zürich, Klusplatz
17:16	NFB 31	Zürich Hegibachplatz
17:16	NFB 31	Schlieren, Zentrum
17:16	T 4	Zürich Tiefenbrunnen, Bahnhof
17:17 +7 min	S1619666	Zürich Flughafen
17:17	NFT 10	Zürich Flughafen, Fracht
17:17	NFT 11	Zürich Rehalp
17:17	T 13	Zürich, Albisgütli
17:17	NFT 13	Zürich, Frankental

## Connections Macro






**SBB Connections** {connections-macro}

Search for sbb connections

## Parameter

Name	Description	Type	This is a required field	Default	Values
From station <code>id</code>		string	✗		
<code>station</code>		string	✗		
Destination <code>to-id</code>	Enter here a preset destination.	string	✗		
<code>to</code>		string	✗		
Show the from field <code>editFrom</code>	Show the from field to change the departure station.	boolean	✗	true	
Show the destination field <code>editDestination</code>	Show the destination field to change the station.	boolean	✗	true	
Change Date & Time <code>editDate</code>		boolean	✗	true	
set departure or arrival box <code>editDepartureOrArrival</code>		boolean	✗	true	
Floating input form <code>formFloat</code>	If deactivated, after each input group is a line break.	boolean	✗	true	

Width of the input form. <code>formWidth</code>	The width in pixel.	int			
Width of the result container. <code>resultsWidth</code>	The width in pixel.	int			
Autoload <code>autoload</code>	If the departure and the destination is configured, the connections are loaded after the page is ready.	boolean		false	

## Related articles

- [SBB Widgets for Confluence](#) (SBB Widgets for Confluence)

## Support

- [Support Portal](#)
- [Public Issue Tracker](#)