

Sections

This page tells you how to customize sections of the Enterprise Theme.

The layout of the Enterprise Theme is divided into multiple sections, where every section can be configured independently. Sections can be configured either globally or per space. If no space specific section has been configured, the section content configured globally will be displayed in all sections. The content of a section is defined as XHTML, the same markup as Confluence uses itself for content. This allows you to use the same macros and formatting features you already know for your section content.


On this page:

- [Available Sections](#)
- [Customize a section globally](#)
- [Customize a section in a space](#)
- [Section Editor](#)

Related pages:

- [Header and Footer Menus](#)
- [Navigating to the Space Administration](#)

Available Sections




Header	The header section is displayed above any page and blog content and uses the full width of the screen. By default, it contains the Metamenu macro to display the menu and language switcher.
Page Sidebar	The page sidebar section is displayed on the left side of any page content and only visible when visiting pages. By default, it contains the Spacelogo macro to display the logo of the current space, the Page Tree macro to display the navigation tree of the space, the Recently Updated macro to list recent blog posts and the Space Manager macro to see the responsible person for this space, if there is one configured.
Blog Sidebar	The blog sidebar section is displayed on the left side of any blog content and only visible when visiting blog posts. By default, it contains the Spacelogo macro to display the logo of the current space, the Blognavigation macro to navigate blog posts, the Page Tree macro to display the navigation tree of the space, the Recently Updated macro to list recent blog posts and the Space Manager macro to see the responsible person for this space, if there is one configured.
Page Bottom	The page bottom section is displayed at the bottom of any page content and only visible when visiting pages. By default, it contains the Label Editor Box macro to display the label editor, the Comment Box macro to show comments and the Attachment Box macro to list any attachments of the page.

Blog Bottom	The blog bottom section is displayed at the bottom of any blog content and only visible when visiting blog posts. By default, it contains the Labeleditor Box macro to display the label editor, the Comment Box macro to show comments and the Attachment Box macro to list any attachments of the blog post.
Footer	The footer section is displayed at the bottom and uses the full width of the screen. By default, it contains the Metamenu macro to display any footer entries.

Customize a section globally

To customize a section globally:


1. Choose the **cog icon**  , at top right of the screen, then choose **General configuration** (You need Admin rights to see the cog icon).
2. Select **Sections** under **Enterprise Theme** in the left-hand panel. This will show you all the sections with their position visually to help you see where your changes will take effect.
3. Click on any of the sections to customize this section's content.

Confluence Admin

CONFIGURATION

- [General Configuration](#)
- [Further Configuration](#)
- [Backup Administration](#)
- [Manage Referrers](#)
- [Languages](#)
- [Shortcut Links](#)
- [External Gadgets](#)
- [Global Templates and Blueprints](#)
- [Import Templates](#)
- [Mail Servers](#)
- [Recommended Updates](#)
- [Email](#)
- [User Macros](#)
- [In-app Notifications](#)
- [Attachment Storage](#)
- [Spam Prevention](#)
- [PDF Export Language Support](#)
- [Configure Code Macro](#)

Sections




The diagram illustrates the layout of sections in a Confluence page. It shows a 'Header' section at the top. Below it, there is a 'Page Sidebar' on the left and a 'Content' area on the right. Underneath the 'Page Sidebar' is a 'Blog Sidebar'. At the bottom of the content area, there are 'Page Bottom' and 'Blog Bottom' sections. Finally, a 'Footer' section spans the entire width at the very bottom.

Customize a section in a space

To customize a section in a space:

1. Go to the space in which you would like to customize the section.
2. Navigate to the space administration. Please refer to the page [Navigating to the Space Administration](#) if you are unsure how to find it.
3. Select **Sections** under **Enterprise Theme**. This will show you all the sections with their position visually to help you see where your changes will take effect.
4. Click on any of the sections to customize this section's content.




Labels help you to see which sections have been customized globally or use some space specific content. You will either see one of the following labels:

GLOBAL The section currently uses the content configured globally.

CUSTOMIZED The content of the section has been customized for the current space and is different from the content configured globally.

Section Editor

To edit the content of a section you use the same editor as Confluence uses itself. This allows you to use the same macros and formatting features you already know for your section content.



Once you've customized the content of a section, a reset button will be displayed next to the save button which allows you to either:

- **Use Default:** reset the content of the section to the default content for the section (for sections configured globally).
- **Use Global:** reset the content of the section to the content configured globally (for sections customized in a space).